Trackit[®] Android

Version: 14.4.69 Release Notes 05/18/2021



These release notes contain information regarding new functionalities, behaviors, changes, and other new experiences you should expect when using this latest version of the TrackIt Android product.





Enhancement: A new feature created to expand the capabilities of the TrackIt Android app and increase its overall benefit for end users.



Correction: A change intended to remove unexpected behaviors in the TrackIt Android app and improve the overall end user experience.



Process Steps: Step-by-step instructions intended to complete a task associated with the enhancement or correction.

0

Information: General information needed to understand the context, behaviors, and restrictions associated with new enhancements and corrections.



v14.4.69 (05/18/2021)

Enhancements

The following items are newly-implemented features intended to increase end-user productivity throughout TrackIt.



Washout Sensor installation field

(TP1-86)

A new Washout Sensor installation field was added to the Sensor Setup page in TrackIt Android. This field is intended for installers to use while setting up the TrackIt Delivery Cycle Monitoring assembly on customer sites.

12:56 🛔 🛆 🗖 🗖 🖬			₩ € क्रि ⁻⁹⁶⁰ ∥ 4% ®
			12:56 PM May 18 🆙 🏫
< Settings Sensors Setup			
System Type	O Probe	I/O Box Mac Address: 0069	67 🗸 - 111111 🕑
	DCM	Flow Meter Volume Per 0.01	Gallons
Vehicle Number:	1235	Pulse:	
	FIND	Water Meter Installed:	Wash Sensor Installed:
	SCAN BARCODE	Drum Type	Standard 🗸
		DCM Sensor Type	DRS v0 -
		Magnet Count	3
SUBMIT			
	111	0	<



Bluetooth connection status for COMMANDassurance (CA-582)

For COMMANDassurance users, the TrackIt Web Console will now show the Bluetooth connection status on the **System Health Summary** report. Bluetooth connection status will appear under the Probe Communication health aspect to help users determine if the connection between the Sensor Link and vehicle tablet is functioning.



Corrections

The following tickets are improvements upon unexpected user experiences for a more fluid and productive experience throughout TrackIt Android.



Corrected behavior:

Upon initial login to TrackIt Android, the device will now be able to consistently access a valid internet connection.

Previous behavior:

At times, an initial login to TrackIt Android would result in the device hanging without finding a valid internet connection.

